

Spray Drift Awareness



Correct Mixing Order

e u shu

Step 1	Fill the spray tank to at least 70% full. Commence agitation	70%
Step 2	Add any water conditioners Ammonium Sulphate or LI 700*	5
Step 3	Add any Wettable powders (WP) e.g. Axiom® Plus	WP
Step 4	Add any Water Dispersible/Soluble Granules (WG/WDG/DF/SG) e.g. Diuron® WG or Ultro® WG	
Step 5	Allow sufficient time for any granular products to completely disperse	
Step 6	Add any Suspension Concentrate (SC) products e.g. Alpha-Scud®300, Priority®, Veritas®Opti	sc
Step 7	Add any Dispersible concentrate (DC) products e.g. Trivor®, Skope®	PC
Step 8	Add any Suspo-emulsion (SE) e.g. Topnotch [®] or Emulsifiable Concentrate (EC) products e.g. Maxentis [®] , Proviso [®] , Quadrant [®] , Triathlon [®] , Trilogy [®]	SE
Step 9	Fill the spray tank to nearly full	
Step 10	Add any Soluble Liquid (SL) products (including Aqueous Concentrate (AC) products) e.g. Picoflex®, Zulu® XT, MCPA 750	SL/AC
Step 11	Add any SL glyphosate products e.g. Wipe-Out® 450, Wipe-Out® Pro or paraquat products e.g. Spraytop®	SL
Step 12	Add any Oil Dispersion (OD) products	ǰ₽
Step 13	Add adjuvants e.g. BS1000* and Oils e.g. Uptake* or Hasten* last and fill the tank.	

®Registered Trademark of an ADAMA Agricultural Solutions Company. *Registered trademarks. Always check labels of all products to be used for manufacturer's tank mix recommendations. Seek competent advice or perform a jar test if unsure before proceeding. The physical and chemical properties of various manufacturer's formulations may differ. Recommendations for use, handling, storage and disposal of products may also change over time. Please note: This information is not intended to replace the product labels. Always read the complete product label appearing on the container before opening or using products. Product labels also available on **adama.com**

adama.com